

## UME36-PRO Application upgrade via USB Disk Drive

1. From The link in the mail download the software update file (.u36) to your computer.
2. Connect The USB Disk Drive to your computer and copy the UME36-PRO Application file to the root folder of the USB Disk Drive.
3. Start You UME36-PRO, from the 'Main Menu' Choose 'Services' and press OK
4. From the 'Services' menu Chose 'Upgrade', and then 'Upgrade Application now'. The UME36-PRO will auto reboot – this process will take a few seconds.
5. From the 'select upgrade source' menu choose The 'USB Disk Drive' option, insert the USB disk drive to the 'source' USB port.
6. From The 'select upgrade file' menu select the Upgrading file (in case you have more than one version in your USB Disk Drive make Sure to choose the correct and latest version) And press 'OK'
7. Now The UME36-PRO will start the upgrading process, this will take up to 1-2 minutes.
8. The UME36-PRO will display message:



9. The UME36-PRO will auto reboot one last time and will be ready for use.